

Field Software Notice

To: **Users of 5300i UCM Mobile Radios**
Subject: **Software Release**

Platform: **5300i UCM Mobile**
Protocol: **All**
Version Release #: **3.8.14** Part Number: **039-5718-213**
Supersedes Version#: **3.8.6**
Effective Release: **03/06/06**

| <i>Minimum Requirements:</i> | <i>Version</i> | <i>Part Number</i> |
|-------------------------------------|---------------------|--------------------------|
| Corresponding DSP Version: | 3.2.2 (no change) | Embedded in flash |
| Corresponding ROM Boot Version: | 3.3 (no change) | 039-5717-202 |
| Corresponding RAM Download Version: | 1.4 (no change) | Embedded in PC Configure |
| Corresponding PCConfigure Version: | 1.28.0.3 ⇔ 1.28.0.8 | 039-5687-236 |
| Corresponding PCTune Version: | 2.0.2.1 ⇔ 2.0.2.3 | 039-5697-211 |
| Corresponding SMA Version: | 1.2.4 (no change) | 039-5730-201 |

Feature Enhancements

- Comments:

- P25 Trunking:

- Start Scan Hold Timer after Announcement Group call has ended
- Allows entry of Site IDs greater than 63
- Supports setting Failsoft inactivity timer to zero
- Improved Denied Group Call in Radio Wide Scan mode
- Removed conflict between TX Delay Timer and Scan Hold Timer
- Resolved sudden loss of carrier in Failsoft mode
- Increased speed for entry into Failsoft mode
- Improved Announcement Group display update
- Announcement Group Strapping Improvement

Field Software Notice

- **SN_SZ:**

- Start Scan Hold Timer after Announcement Group call has ended
- Supports setting Failsoft inactivity timer to zero
- Improved Denied Group Call in Radio Wide Scan mode
- Removed conflict between TX Delay Timer and Scan Hold Timer
- Eliminates VHF Priority Scan Popping

- **Conventional:**

- Added ability to edit channel spacing on a mixed mode channel with analog transmit enabled
- Eliminates UHF Priority Scan Popping

- **General Improvements:**

- Allows radio to actuate Emergency upon assertion of Input B
- Increased Minimum Task Timer to 10 seconds for uploading/downloading with PCC in P25 Trunking environment